

# FontLab VI Multi-Seat License Setup

This particular instruction is for those who purchased a “floating” (multi-seat) serial number and need to setup the default license manager for it. By default, we suggest to use RLM (Reprise License Manager) software. But you also have an alternative as we support KeyServer ([Sassafras Software](#)) too. Please contact [Fontlab Support](#) if you need to switch from RLM to KeyServer (or back).

## Installation

To install FontLab 8 in a lab, you need to download the file “multi\_license\_activation\_package.zip”.

**This file includes:**

1. RLM (Reprise License Manager) Software - the server app for managing floating (multi-seat) licenses. You must install this first. We deliver both the Mac and Windows version of RLM in this package. If your Server OS differs from your workstations’ operating system, just install the appropriate version for the server.
2. RLM Documentation from Reprise Software. You can refer to it as well.
3. Template license file “com.fontlab.fl.lic” for workstations.
4. This instruction.

## License Manager/Server Setup


### ⓘ Attention

Please you should NOT run Fontlab 8 and enter the serial number in the **Activation** dialog prior to the License Server setup.

**To setup the License Server and activate your license please follow these steps carefully:**

1. Choose a computer to be the License Manager Server. It can be the same computer where you will work with FontLab but usually it will be a dedicated Server.
2. Copy the RLM folder (corresponding to your server OS) from this package to any place on your Server computer. We recommend you use the common folder for Server applications. This can be the **Applications** folder on macOS or **Program Files** on Windows.


3. Launch the executable file **rlm** (rlm.exe) found in the **RLM** folder. A Terminal session will be opened with “Server Started” printed in the window.
4. Open your browser and start the **Reprise License Server Administration** tool – just enter **localhost:5054** in the address string and press .



- 4.1. Click on the **ACTIVATE LICENSE** button in the left side menu and then on **Begin License Activation**.
  - 4.2. Choose **Other** (URL) and type [www.register.fontlab.com](http://www.register.fontlab.com) in the text box.
  - 4.3. Set **ISV to:** fontlab and enter your serial number in the **License Activation Key** field. This is the only place where you will enter the serial number. You will not need to enter the serial number on the workstations.
  - 4.4. In the **License Server or Node-lock hostid** text box RLM automatically prints the **host ID** of the computer. This host ID will be used as an anchor for the generated license.
- You should enter the number of purchased licenses (seats) in the **License count** text box.
- 4.5. The full path of your newly created license file will be shown at this step. (`user folder\activate1.lic` or `RLM folder\activate1.lic` are the most probable).

**Remember this Path.**

4.6. Verify all your input data and click on the **REQUEST LICENSE** button.



4.7. Go to the path mentioned in 4.5 just above and **move the license file right into the RLM folder** (where rlm executable was just run from). We recommend you change the file name to “FL8\_server.lic” or “FL8\_20seats.lic”. **Note that the file name extension must be “lic”.**

Changing the content of this file will make the license invalid so do not allow anyone to change it in any way. Make a backup and store it in a safe place at the end of activation.

4.8. If the process does not finish successfully an error message will be shown. Try to repair the situation and perform your request again. If you have any trouble, please send us a problem report at [support.fontlab.com](mailto:support.fontlab.com).

4.9. Click on the **RESTART LICENSE SERVER** button to refresh the Server with the newly generated license.

The installation of the RLM Server is now complete.

#### **Note**

The **RLM application** (rlm.exe on Windows or rlm executable on Mac) must be relaunched at every server reboot. On Windows you can use the button **Manage Windows Service** in the RLM Admin tool. On Mac OS X, add RLM to the

list of startup applications. See the “Running the rlm server as a service on Windows” or “Starting the rlm server at system boot time on Unix systems” parts of the **RLM documentation** for details.

# Workstations Setup

Now you must prepare a license file for all workstations where FontLab is to be installed.

1. Find the template file “com.fontlab.fl.lic” in the package “multi\_license\_activation\_package.zip”. This file contains only two lines:

```
HOST <ServerName> ANY 5053
ISV fontlab
```

2. Edit the file in a text editor and replace the parameter with the network name or numeric IP address of your server - the one where the server **RLM** program was just installed. The server name or IP address must be pingable. In other words, sending the command ping to this name or IP address from workstations must work successfully.

The result file can look like the following examples:

```
HOST our_best_server ANY 5053
ISV fontlab
```

or

```
HOST 192.168.1.5 ANY 5053
ISV fontlab
```

3. Copy the newly edited “com.fontlab.fl.lic” file to all your workstations into the following folders:

<System Disk>:\Program Data\Fontlab\ on Windows

or

Macintosh HD/Library/Preferences/ on macOS.

4. Now install FontLab 8 Application on each of the workstations.

Your installation is now complete.